



eYS3D
Microelectronics

eYs3D Linux SDK

testTag007

Generated by Doxygen 1.8.13

Contents

1	Introduction	1
2	Class Index	3
2.1	Class List	3
3	File Index	5
3.1	File List	5
4	Class Documentation	7
4.1	AccelerationTag Struct Reference	7
4.2	APC_META_DATA Struct Reference	7
4.3	APCImageType Struct Reference	7
4.4	CompassTag Struct Reference	8
4.5	DECIMATION_PARAMS Struct Reference	8
4.6	DEVINFORMATIONEX Class Reference	8
4.6.1	Member Data Documentation	9
4.6.1.1	nChipID	9
4.6.1.2	nDevType	9
4.6.1.3	strDevName	9
4.6.1.4	strDevPath	9
4.6.1.5	wPID	9
4.6.1.6	wUsbNode	10
4.6.1.7	wVID	10
4.7	eSPCtrl_RectLogData Struct Reference	10
4.7.1	Member Data Documentation	11

4.7.1.1	CamDist1	11
4.7.1.2	CamDist2	11
4.7.1.3	CamMat1	11
4.7.1.4	CamMat2	11
4.7.1.5	Date	11
4.7.1.6	InImgHeight	11
4.7.1.7	InImgWidth	11
4.7.1.8	LRotaMat	11
4.7.1.9	NewCamMat1	12
4.7.1.10	NewCamMat2	12
4.7.1.11	nLineBuffers	12
4.7.1.12	OutImgHeight	12
4.7.1.13	OutImgWidth	12
4.7.1.14	RECT_AvgErr	12
4.7.1.15	RECT_Crop_Col_BG_L	12
4.7.1.16	RECT_Crop_Col_ED_L	12
4.7.1.17	RECT_Crop_Row_BG	12
4.7.1.18	RECT_Crop_Row_ED	12
4.7.1.19	RECT_CropEnable	13
4.7.1.20	RECT_Scale_Col_M	13
4.7.1.21	RECT_Scale_Col_N	13
4.7.1.22	RECT_Scale_Row_M	13
4.7.1.23	RECT_Scale_Row_N	13
4.7.1.24	RECT_ScaleEnable	13
4.7.1.25	RECT_ScaleHeight	13
4.7.1.26	RECT_ScaleWidth	13
4.7.1.27	RotaMat	13
4.7.1.28	RRotaMat	13
4.7.1.29	TranMat	14
4.7.1.30	uByteArray	14
4.8	GyroTag Struct Reference	14
4.9	packet_s Struct Reference	14
4.10	PointCloudInfo Struct Reference	15
4.10.1	Detailed Description	15
4.11	POST_PROCESS_PARAMS Struct Reference	16
4.12	tagAPC_STREAM_INFO Struct Reference	16
4.13	tagDEVINFORMATION Struct Reference	16
4.14	tagDEVSEL Struct Reference	16
4.15	tagKEEP_DATA_CTRL Struct Reference	17
4.16	tagZDTableInfo Struct Reference	17

CONTENTS	iii
5 File Documentation	19
5.1 eSPDI/eSPDI.h File Reference	19
5.2 eSPDI/eSPDI_def.h File Reference	19
5.2.1 Detailed Description	27
Index	29

Chapter 1

Introduction

This document describes the usage of eYs3D Linux SDK

What's inside the SDK

Table 1.1 File List

Folder	Filename	Description
bin	All files	sample executables on Linux platform
console_tester	All files	a console program demonstrating how to use the APIs defined in eSPDI.h
cfg	All files	configuration files
eSPDI	eSPDI.h	functions definitions
	eSPDI_def.h	error/data type definitions
	eSPDI↔ version.h	SDK version declaration header
DMPreview	All files	a sample project demonstrating how to open multiple devices in an application

Chapter 2

Class Index

2.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

AccelerationTag	7
APC_META_DATA	7
APCImageType	7
CompassTag	8
DECIMATION_PARAMS	8
DEVINFORMATIONEX	8
eSPCtrl_RectLogData	10
GyroTag	14
packet_s	14
PointCloudInfo	15
POST_PROCESS_PARAMS	16
tagAPC_STREAM_INFO	16
tagDEVINFORMATION	16
tagDEVSEL	16
tagKEEP_DATA_CTRL	17
tagZDTableInfo	17

Chapter 3

File Index

3.1 File List

Here is a list of all documented files with brief descriptions:

eSPDI/ eSPDI.h	
Functions definitions	19
eSPDI/ eSPDI_def.h	
Error/data type definitions	19
eSPDI/ eSPDI_version.h	??

Chapter 4

Class Documentation

4.1 AccelerationTag Struct Reference

Public Attributes

- short **x**
- short **y**
- short **z**

The documentation for this struct was generated from the following file:

- [eSPDI/eSPDI_def.h](#)

4.2 APC_META_DATA Struct Reference

Public Attributes

- uint8_t **protocolVersion**
- uint8_t **payloadSize**
- union {
 uint8_t **payload** [256]
};

The documentation for this struct was generated from the following file:

- [eSPDI/eSPDI.h](#)

4.3 APCImageType Struct Reference

Public Types

- enum **Value** {
 IMAGE_UNKNOWN = -1, **COLOR_YUY2** = 0, **COLOR_RGB24**, **COLOR_MJPEG**,
 COLOR_UYVY, **DEPTH_8BITS** = 100, **DEPTH_8BITS_0x80**, **DEPTH_11BITS**,
 DEPTH_14BITS }

Static Public Member Functions

- static bool **IsImageColor** (APCImageType::Value type)
- static bool **IsImageDepth** (APCImageType::Value type)
- static bool **IsDepthDataTypeDisparity** (WORD dataType)
- static APCImageType::Value **DepthDataTypeToDepthImageType** (WORD dataType)

The documentation for this struct was generated from the following file:

- [eSPDI/eSPDI_def.h](#)

4.4 CompassTag Struct Reference

Public Attributes

- short **x**
- short **y**
- short **z**

The documentation for this struct was generated from the following file:

- [eSPDI/eSPDI_def.h](#)

4.5 DECIMATION_PARAMS Struct Reference

Public Attributes

- int **decimation_sub_sample_factor** = 2

The documentation for this struct was generated from the following file:

- [eSPDI/eSPDI_def.h](#)

4.6 DEVINFORMATIONEX Class Reference

Public Member Functions

- [DEVINFORMATIONEX](#) & **operator=** (const [DEVINFORMATIONEX](#) &rhs)
- [DEVINFORMATIONEX](#) & **operator=** (const [DEVINFORMATION](#) &rhs)
- **DEVINFORMATIONEX** (const [DEVINFORMATIONEX](#) &rhs)

Public Attributes

- unsigned short [wPID](#) { 0 }
- unsigned short [wVID](#) { 0 }
- char [strDevName](#) [512] { '\0' }
- char [strDevPath](#) [512] { '\0' }
- unsigned short [nChipID](#) { 0 }
- unsigned short [nDevType](#) { 0 }
- unsigned short [wUsbNode](#) { 0xffff }

4.6.1 Member Data Documentation

4.6.1.1 unsigned short DEVINFORMATIONEX::nChipID { 0 }

chip ID, 0x18 for AXES1, 0x1C for KIWI, 0x15 for PUMA

4.6.1.2 unsigned short DEVINFORMATIONEX::nDevType { 0 }

chip enum value, see `APC_DEVICE_TYPE`

4.6.1.3 char DEVINFORMATIONEX::strDevName[512] { '\0' }

device name

4.6.1.4 char DEVINFORMATIONEX::strDevPath[512] { '\0' }

device path

4.6.1.5 unsigned short DEVINFORMATIONEX::wPID { 0 }

product ID

Table 4.1 PID List

Chip Name	Chip ID	PID
AXES1	0x18	0x0568
		0x0668
		0x0113
		0x0115
		0x0116
KIWI	0x1C	0x0118
PUMA	0x15	0x0112
		0x0120

4.6.1.6 unsigned short DEVINFORMATIONEX::wUsbNode { 0xffff }

USB Node representing djb2_hash hashed port numbers. Developers compare its equality to judge if devices share the same port.

4.6.1.7 unsigned short DEVINFORMATIONEX::wVID { 0 }

vender ID, 0x1E4E for ApcDI device

The documentation for this class was generated from the following file:

- [eSPDI/eSPDI_def.h](#)

4.7 eSPCtrl_RectLogData Struct Reference

Public Attributes

- union {
 - unsigned char [uByteArray](#) [1024]
 - struct {
 - unsigned short [InImgWidth](#)
 - unsigned short [InImgHeight](#)
 - unsigned short [OutImgWidth](#)
 - unsigned short [OutImgHeight](#)
 - int [RECT_ScaleEnable](#)
 - int [RECT_CropEnable](#)
 - unsigned short [RECT_ScaleWidth](#)
 - unsigned short [RECT_ScaleHeight](#)
 - float [CamMat1](#) [9]
 - float [CamDist1](#) [8]
 - float [CamMat2](#) [9]
 - float [CamDist2](#) [8]
 - float [RotaMat](#) [9]
 - float [TranMat](#) [3]
 - float [LRotaMat](#) [9]
 - float [RRotaMat](#) [9]
 - float [NewCamMat1](#) [12]
 - float [NewCamMat2](#) [12]
 - unsigned short [RECT_Crop_Row_BG](#)
 - unsigned short [RECT_Crop_Row_ED](#)
 - unsigned short [RECT_Crop_Col_BG_L](#)
 - unsigned short [RECT_Crop_Col_ED_L](#)
 - unsigned char [RECT_Scale_Col_M](#)
 - unsigned char [RECT_Scale_Col_N](#)
 - unsigned char [RECT_Scale_Row_M](#)
 - unsigned char [RECT_Scale_Row_N](#)
 - float [RECT_AvgErr](#)
 - unsigned short [nLineBuffers](#)
 - float [ReProjectMat](#) [16]
 - float [ParameterRatio](#) [2]
 - float [LR_cam_K_temperature](#) [2]
 - float [LR_cam_thermal_variation_rate_of_focal](#) [2]
 - float [depth_comp_pars](#) [2]


```

    long Date
    char type
    char version [4]
}
};

```

4.7.1 Member Data Documentation

4.7.1.1 float eSPCtrl_RectLogData::CamDist1[8]

Left Camera Distortion Matrix k1, k2, p1, p2, k3, k4, k5, k6 k1~k6 : radial distort ; p1,p2 : tangential distort

4.7.1.2 float eSPCtrl_RectLogData::CamDist2[8]

Right Camera Distortion Matrix k1, k2, p1, p2, k3, k4, k5, k6 k1~k6 : radial distort ; p1,p2 : tangential distort

4.7.1.3 float eSPCtrl_RectLogData::CamMat1[9]

Left Camera Matrix fx, 0, cx, 0, fy, cy, 0, 0, 1 fx,fy : focus ; cx,cy : principle point

4.7.1.4 float eSPCtrl_RectLogData::CamMat2[9]

Right Camera Matrix fx, 0, cx, 0, fy, cy, 0, 0, 1 fx,fy : focus ; cx,cy : principle point

4.7.1.5 long eSPCtrl_RectLogData::Date

pars for compensating disparity value, Formula: $\text{new_disp_vaule} = \text{disp_value} * \text{depth_comp_pars}[0] + \text{depth_comp_pars}[1]$

4.7.1.6 unsigned short eSPCtrl_RectLogData::InImgHeight

Input image height

4.7.1.7 unsigned short eSPCtrl_RectLogData::InImgWidth

Input image width(SideBySide image)

4.7.1.8 float eSPCtrl_RectLogData::LRotaMat[9]

3x3 rectification transform (rotation matrix) for the left camera. $\begin{bmatrix} [0] & [1] & [2] \\ [3] & [4] & [5] \\ [6] & [7] & [8] \end{bmatrix} \begin{bmatrix} |Xcl| \\ |Ycl| \\ |Zcl| \end{bmatrix} * \begin{bmatrix} |Xcl| \\ |Ycl| \\ |Zcl| \end{bmatrix} \Rightarrow cl = \text{left camera coordinate}$

4.7.1.9 float eSPCtrl_RectLogData::NewCamMat1[12]

3x4 projection matrix in the (rectified) coordinate systems for the left camera. $fx' \ 0 \ cx' \ 0 \ 0 \ fy' \ cy' \ 0 \ 0 \ 0 \ 1 \ 0 \ fx',fy'$: rectified focus ; cx', cy' : rectified principle point

4.7.1.10 float eSPCtrl_RectLogData::NewCamMat2[12]

3x4 projection matrix in the (rectified) coordinate systems for the right camera. $fx' \ 0 \ cx' \ TranMat[0]* \ 0 \ fy' \ cy' \ 0 \ 0 \ 0 \ 1 \ 0 \ fx',fy'$: rectified focus ; cx', cy' : rectified principle point

4.7.1.11 unsigned short eSPCtrl_RectLogData::nLineBuffers

Linebuffer for Hardware limitation < 60

4.7.1.12 unsigned short eSPCtrl_RectLogData::OutImgHeight

Output image height

4.7.1.13 unsigned short eSPCtrl_RectLogData::OutImgWidth

Output image width(SideBySide image)

4.7.1.14 float eSPCtrl_RectLogData::RECT_AvgErr

Reprojection error

4.7.1.15 unsigned short eSPCtrl_RectLogData::RECT_Crop_Col_BG_L

Rectidied image crop column begin

4.7.1.16 unsigned short eSPCtrl_RectLogData::RECT_Crop_Col_ED_L

Rectidied image crop column end

4.7.1.17 unsigned short eSPCtrl_RectLogData::RECT_Crop_Row_BG

Rectidied image crop row begin

4.7.1.18 unsigned short eSPCtrl_RectLogData::RECT_Crop_Row_ED

Rectidied image crop row end

4.7.1.19 int eSPCtrl_RectLogData::RECT_CropEnable

Rectified image crop

4.7.1.20 unsigned char eSPCtrl_RectLogData::RECT_Scale_Col_M

Rectified image scale column factor M

4.7.1.21 unsigned char eSPCtrl_RectLogData::RECT_Scale_Col_N

Rectified image scale column factor N Rectified image scale column ratio = Scale_Col_N/ Scale_Col_M

4.7.1.22 unsigned char eSPCtrl_RectLogData::RECT_Scale_Row_M

Rectified image scale row factor M

4.7.1.23 unsigned char eSPCtrl_RectLogData::RECT_Scale_Row_N

Rectified image scale row factor N

4.7.1.24 int eSPCtrl_RectLogData::RECT_ScaleEnable

Rectified image scale

4.7.1.25 unsigned short eSPCtrl_RectLogData::RECT_ScaleHeight

Input image height(Single image) *RECT_Scale_Row_N /RECT_Scale_Row_M

4.7.1.26 unsigned short eSPCtrl_RectLogData::RECT_ScaleWidth

Input image width(Single image) *RECT_Scale_Col_N /RECT_Scale_Col_M

4.7.1.27 float eSPCtrl_RectLogData::RotaMat[9]

Rotation matrix between the left and right camera coordinate systems. $\begin{bmatrix} [0] & [1] & [2] \\ |Xcr| & [3] & [4] & [5] \\ * & |Ycr| \end{bmatrix} \Rightarrow cr$
= right camera coordinate $\begin{bmatrix} [6] & [7] & [8] \\ |Zcr| \end{bmatrix}$

4.7.1.28 float eSPCtrl_RectLogData::RRotaMat[9]

3x3 rectification transform (rotation matrix) for the left camera. $\begin{bmatrix} [0] & [1] & [2] \\ |Xcr| & [3] & [4] & [5] \\ * & |Ycr| \end{bmatrix} \Rightarrow cr$ = right camera coordinate $\begin{bmatrix} [6] & [7] & [8] \\ |Zcr| \end{bmatrix}$

4.7.1.29 float eSPCtrl_RectLogData::TranMat[3]

Translation vector between the coordinate systems of the cameras. $|[0]| |Xcr| | [1]| + |Ycr| => cr = \text{right camera coordinate } |[2]| |Zcr|$

4.7.1.30 unsigned char eSPCtrl_RectLogData::uByteArray[1024]

union data defined as below struct { }

The documentation for this struct was generated from the following file:

- [eSPDI/eSPDI_def.h](#)

4.8 GyroTag Struct Reference

Public Attributes

- short **x**
- short **y**
- short **z**

The documentation for this struct was generated from the following file:

- [eSPDI/eSPDI_def.h](#)

4.9 packet_s Struct Reference

Public Attributes

- int **len**
- int **serial**
- bool **bisRGB**
- bool **bisReady**
- union {
 - unsigned char **buffer_yuyv** [2 *2560 *2560]
 - unsigned char **buffer_RGB** [3 *2560 *2560]

The documentation for this struct was generated from the following file:

- [eSPDI/eSPDI_def.h](#)

4.10 PointCloudInfo Struct Reference

```
#include <eSPDI_def.h>
```

Public Attributes

- float **centerX**
- float **centerY**
- float **focalLength**
- float **disparityToW** [2048]
- int **disparity_len**
- WORD **wDepthType**
- float **fx1**
- float **fy1**
- float **fx2**
- float **fy2**
- float **cx1**
- float **cy1**
- float **cx2**
- float **cy2**
- float **Tx**
- int **depth_image_edian**
- float **focalLength_K**
- float **baseline_K**
- float **diff_K**
- float **slaveDeviceCamMat2** [9]
- float **slaveDeviceRotaMat** [9]
- float **slaveDeviceTranMat** [3]
- float **depthScaleRatio**
- bool **blsMIPISplit**

4.10.1 Detailed Description

Parameters

<i>M_dst</i>	input camera matrix of RGB-lens, including intrinsic parameters, such as RectifyLog-CamMat2 (M3). The buffer size is 9.
<i>R_dst_to_src</i>	input rotation matrix of dst-lens to src-lens, dst is the camera at left side, src is the camera at right side, such as RectifyLog-RotaMat (R31). The buffer size is 9.
<i>T_dst_to_src</i>	input translation matrix of dst-lens to src-lens, such as RectifyLog-TranMat (T13). The buffer size is 3.
<i>depthScaleRatio</i>	Fill in scaled depth height divided by rectified image output height. This ratio is needed when developers invoke APC_DecimationFilter to resize image depth.

The documentation for this struct was generated from the following file:

- [eSPDI/eSPDI_def.h](#)

4.11 POST_PROCESS_PARAMS Struct Reference

Public Attributes

- int **spatial_filter_kernel_size** = 5
- float **spatial_filter_outlier_threshold** = 16

The documentation for this struct was generated from the following file:

- [eSPDI/eSPDI_def.h](#)

4.12 tagAPC_STREAM_INFO Struct Reference

Public Attributes

- int **nWidth**
- int **nHeight**
- BOOL **bFormatMJPG**

The documentation for this struct was generated from the following file:

- [eSPDI/eSPDI_def.h](#)

4.13 tagDEVINFORMATION Struct Reference

Public Attributes

- unsigned short **wPID**
- unsigned short **wVID**
- char * **strDevName**
- unsigned short **nChipID**
- unsigned short **nDevType**

The documentation for this struct was generated from the following file:

- [eSPDI/eSPDI_def.h](#)

4.14 tagDEVSEL Struct Reference

Public Attributes

- int **index**

The documentation for this struct was generated from the following file:

- [eSPDI/eSPDI_def.h](#)

4.15 tagKEEP_DATA_CTRL Struct Reference

Public Attributes

- bool **blsSerialNumberKeep**
- bool **blsSensorPositionKeep**
- bool **blsRectificationTableKeep**
- bool **blsZDTableKeep**
- bool **blsCalibrationLogKeep**

The documentation for this struct was generated from the following file:

- [eSPDI/eSPDI_def.h](#)

4.16 tagZDTableInfo Struct Reference

Public Attributes

- int **nIndex**
- int **nDataType**

The documentation for this struct was generated from the following file:

- [eSPDI/eSPDI_def.h](#)

Chapter 5

File Documentation

5.1 eSPDI/eSPDI.h File Reference

functions definitions

```
#include "eSPDI_def.h"
#include "eSPDI_version.h"
#include <stdlib.h>
#include <vector>
#include <stdint>
Include dependency graph for eSPDI.h:
```

5.2 eSPDI/eSPDI_def.h File Reference

error/data type definitions

```
#include <cstring>
Include dependency graph for eSPDI_def.h: This graph shows which files directly or indirectly include this file:
```

Classes

- struct [packet_s](#)
- struct [tagDEVINFORMATION](#)
- struct [POST_PROCESS_PARAMS](#)
- struct [DECIMATION_PARAMS](#)
- struct [tagDEVSEL](#)
- struct [tagAPC_STREAM_INFO](#)
- struct [tagZDTableInfo](#)
- class [DEVINFORMATIONEX](#)
- struct [tagKEEP_DATA_CTRL](#)
- struct [eSPCtrl_RectLogData](#)
- struct [GyroTag](#)
- struct [AccelerationTag](#)
- struct [CompassTag](#)
- struct [APCImageType](#)
- struct [PointCloudInfo](#)

Macros

- #define **MAX_DEV_COUNT** 20
- #define **MAX_TOTAL_DEV_CONT** (MAX_DEV_COUNT * 2 + MAX_DEV_COUNT)
- #define **SIMPLE_DEV_START_IDX** (MAX_TOTAL_DEV_CONT - (MAX_DEV_COUNT))
- #define **APC_OK** 0
- #define **APC_NoDevice** -1
- #define **APC_NullPtr** -2
- #define **APC_ErrBufLen** -3
- #define **APC_Init_Fail** -4
- #define **APC_NoZDTable** -5
- #define **APC_READFLASHFAIL** -6
- #define **APC_WRITEFLASHFAIL** -7
- #define **APC_VERIFY_DATA_FAIL** -8
- #define **APC_KEEP_DATA_FAIL** -9
- #define **APC_RECT_DATA_LEN_FAIL** -10
- #define **APC_RECT_DATA_PARSING_FAIL** -11
- #define **APC_RET_BAD_PARAM** -12
- #define **APC_RET_OPEN_FILE_FAIL** -13
- #define **APC_NO_CALIBRATION_LOG** -14
- #define **APC_POSTPROCESS_INIT_FAIL** -15
- #define **APC_POSTPROCESS_NOT_INIT** -16
- #define **APC_POSTPROCESS_FRAME_FAIL** -17
- #define **APC_NotSupport** -18
- #define **APC_GET_RES_LIST_FAIL** -19
- #define **APC_READ_REG_FAIL** -20
- #define **APC_WRITE_REG_FAIL** -21
- #define **APC_SET_FPS_FAIL** -22
- #define **APC_VIDEO_RENDER_FAIL** -23
- #define **APC_OPEN_DEVICE_FAIL** -24
- #define **APC_FIND_DEVICE_FAIL** -25
- #define **APC_GET_IMAGE_FAIL** -26
- #define **APC_NOT_SUPPORT_RES** -27
- #define **APC_CALLBACK_REGISTER_FAIL** -28
- #define **APC_CLOSE_DEVICE_FAIL** -29
- #define **APC_GET_CALIBRATIONLOG_FAIL** -30
- #define **APC_SET_CALIBRATIONLOG_FAIL** -31
- #define **APC_DEVICE_NOT_SUPPORT** -32
- #define **APC_DEVICE_BUSY** -33
- #define **APC_DEVICE_TIMEOUT** -34
- #define **APC_IO_SELECT_EINTR** -35
- #define **APC_IO_SELECT_ERROR** -36
- #define **APC_ILLEGAL_ANGLE** -40
- #define **APC_ILLEGAL_STEP** -41
- #define **APC_ILLEGAL_TIMEPERSTEP** -42
- #define **APC_MOTOR_RUNNING** -43
- #define **APC_GETSENSORREG_FAIL** -44
- #define **APC_SETSENSORREG_FAIL** -45
- #define **APC_READ_X_AXIS_FAIL** -46
- #define **APC_READ_Y_AXIS_FAIL** -47
- #define **APC_READ_Z_AXIS_FAIL** -48
- #define **APC_READ_PRESS_DATA_FAIL** -49
- #define **APC_READ_TEMPERATURE_FAIL** -50
- #define **APC_RETURNHOME_RUNNING** -51
- #define **APC_MOTOTSTOP_BY_HOME_INDEX** -52

- **#define APC_MOTOTSTOP_BY_PROTECT_SCHEME** -53
- **#define APC_MOTOTSTOP_BY_NORMAL** -54
- **#define APC_ILLEGAL_FIRMWARE_VERSION** -55
- **#define APC_ILLEGAL_STEPPERTIME** -56
- **#define APC_GET_PU_PROP_VAL_FAIL** -60
- **#define APC_SET_PU_PROP_VAL_FAIL** -61
- **#define APC_GET_CT_PROP_VAL_FAIL** -62
- **#define APC_SET_CT_PROP_VAL_FAIL** -63
- **#define APC_GET_CT_PROP_RANGE_STEP_FAIL** -64
- **#define APC_GET_PU_PROP_RANGE_STEP_FAIL** -65
- **#define APC_INVALID_USERDATA** -70
- **#define APC_MAP_LUT_FAIL** -71
- **#define APC_APPEND_TO_FILE_FRONT_FAIL** -72
- **#define APC_TOO_MANY_DEVICE** -80
- **#define APC_ACCESS_MP4_EXTRA_DATA_FAIL** -81
- **#define BIT_SET**(a, b) ((a) |= (1<<(b)))
- **#define BIT_CLEAR**(a, b) ((a) &= ~(1<<(b)))
- **#define BIT_FLIP**(a, b) ((a) ^= (1<<(b)))
- **#define BIT_CHECK**(a, b) ((a) & (1<<(b)))
- **#define FG_Address_1Byte** 0x01
- **#define FG_Address_2Byte** 0x02
- **#define FG_Value_1Byte** 0x10
- **#define FG_Value_2Byte** 0x20
- **#define FG_MULTI_BYTE_RW_SELECTOR_4** 0x200
- **#define EVENT_BUFFER_SHM_COLOR** "/shm_ring_buffer_color"
- **#define EVENT_BUFFER_SHM_DEPTH** "/shm_ring_buffer_depth"
- **#define EVENT_BUFFER_SHM** "/shm_ring_buffer"
- **#define CMD_FIFO_PATH** "/tmp/cmdfifo"
- **#define ZD_PATH** "/tmp/zd_addr"
- **#define RECTIFY_LOG_PATH** "/tmp/rectifylog_addr"
- **#define SRB_LENGTH** 10
- **#define CHIPID_ADDR** 0xf014
- **#define GRAPE_CHIPID_ADDR** 0xf004
- **#define SERIAL_2BIT_ADDR** 0xf0fe
- **#define APC_DEPTH_DATA_OFF_RAW** 0 /* raw (depth off, only raw color) */
- **#define APC_DEPTH_DATA_DEFAULT** APC_DEPTH_DATA_OFF_RAW /* raw (depth off, only gray raw color) */
- **#define APC_DEPTH_DATA_8_BITS** 1 /* rectify, 1 byte per pixel */
- **#define APC_DEPTH_DATA_14_BITS** 2 /* rectify, 2 byte per pixel */
- **#define APC_DEPTH_DATA_8_BITS_x80** 3 /* rectify, 2 byte per pixel but using 1 byte only */
- **#define APC_DEPTH_DATA_11_BITS** 4 /* rectify, 2 byte per pixel but using 11 bit only */
- **#define APC_DEPTH_DATA_OFF_RECTIFY** 5 /* rectify (depth off, only rectify raw color) */
- **#define APC_DEPTH_DATA_8_BITS_RAW** 6 /* raw */
- **#define APC_DEPTH_DATA_14_BITS_RAW** 7 /* raw */
- **#define APC_DEPTH_DATA_8_BITS_x80_RAW** 8 /* raw */
- **#define APC_DEPTH_DATA_11_BITS_RAW** 9 /* raw */
- **#define APC_DEPTH_DATA_14_BITS_COMBINED_RECTIFY** 11
- **#define APC_DEPTH_DATA_11_BITS_COMBINED_RECTIFY** 13
- **#define APC_DEPTH_DATA_OFF_BAYER_RAW** 14
- **#define APC_DEPTH_DATA_INTERLEAVE_MODE_OFFSET** 16
- **#define APC_DEPTH_DATA_ILM_OFF_RAW** (APC_DEPTH_DATA_OFF_RAW + APC_DEPTH_DATA_INTERLEAVE_MODE_OFFSET) /* raw (depth off, only raw color) */
- **#define APC_DEPTH_DATA_ILM_DEFAULT** (APC_DEPTH_DATA_DEFAULT + APC_DEPTH_DATA_INTERLEAVE_MODE_OFFSET) /* raw (depth off, only raw color) */

- **#define APC_DEPTH_DATA_ILM_8_BITS** (APC_DEPTH_DATA_8_BITS + APC_DEPTH_DATA_INTERLEAVE_MODE_OFFSET) /* rectify, 1 byte per pixel */
- **#define APC_DEPTH_DATA_ILM_14_BITS** (APC_DEPTH_DATA_14_BITS + APC_DEPTH_DATA_INTERLEAVE_MODE_OFFSET) /* rectify, 2 byte per pixel */
- **#define APC_DEPTH_DATA_ILM_8_BITS_x80** (APC_DEPTH_DATA_8_BITS_x80 + APC_DEPTH_DATA_INTERLEAVE_MODE_OFFSET) /* rectify, 2 byte per pixel but using 1 byte only */
- **#define APC_DEPTH_DATA_ILM_11_BITS** (APC_DEPTH_DATA_11_BITS + APC_DEPTH_DATA_INTERLEAVE_MODE_OFFSET) /* rectify, 2 byte per pixel but using 11 bit only */
- **#define APC_DEPTH_DATA_ILM_OFF_RECTIFY** (APC_DEPTH_DATA_OFF_RECTIFY + APC_DEPTH_DATA_INTERLEAVE_MODE_OFFSET) /* rectify (depth off, only rectify color) */
- **#define APC_DEPTH_DATA_ILM_8_BITS_RAW** (APC_DEPTH_DATA_8_BITS_RAW + APC_DEPTH_DATA_INTERLEAVE_MODE_OFFSET) /* raw */
- **#define APC_DEPTH_DATA_ILM_14_BITS_RAW** (APC_DEPTH_DATA_14_BITS_RAW + APC_DEPTH_DATA_INTERLEAVE_MODE_OFFSET) /* raw */
- **#define APC_DEPTH_DATA_ILM_8_BITS_x80_RAW** (APC_DEPTH_DATA_8_BITS_x80_RAW + APC_DEPTH_DATA_INTERLEAVE_MODE_OFFSET) /* raw */
- **#define APC_DEPTH_DATA_ILM_11_BITS_RAW** (APC_DEPTH_DATA_11_BITS_RAW + APC_DEPTH_DATA_INTERLEAVE_MODE_OFFSET) /* raw */
- **#define APC_DEPTH_DATA_ILM_14_BITS_COMBINED_RECTIFY** (APC_DEPTH_DATA_14_BITS_COMBINED_RECTIFY + APC_DEPTH_DATA_INTERLEAVE_MODE_OFFSET)
- **#define APC_DEPTH_DATA_ILM_11_BITS_COMBINED_RECTIFY** (APC_DEPTH_DATA_11_BITS_COMBINED_RECTIFY + APC_DEPTH_DATA_INTERLEAVE_MODE_OFFSET)
- **#define APC_DEPTH_DATA_SCALE_DOWN_MODE_OFFSET** 32
- **#define APC_DEPTH_DATA_SCALE_DOWN_OFF_RAW** (APC_DEPTH_DATA_OFF_RAW + APC_DEPTH_DATA_SCALE_DOWN_MODE_OFFSET) /* raw (depth off, only raw color) */
- **#define APC_DEPTH_DATA_SCALE_DOWN_DEFAULT** (APC_DEPTH_DATA_DEFAULT + APC_DEPTH_DATA_SCALE_DOWN_MODE_OFFSET) /* raw (depth off, only raw color) */
- **#define APC_DEPTH_DATA_SCALE_DOWN_8_BITS** (APC_DEPTH_DATA_8_BITS + APC_DEPTH_DATA_SCALE_DOWN_MODE_OFFSET) /* rectify, 1 byte per pixel */
- **#define APC_DEPTH_DATA_SCALE_DOWN_14_BITS** (APC_DEPTH_DATA_14_BITS + APC_DEPTH_DATA_SCALE_DOWN_MODE_OFFSET) /* rectify, 2 byte per pixel */
- **#define APC_DEPTH_DATA_SCALE_DOWN_8_BITS_x80** (APC_DEPTH_DATA_8_BITS_x80 + APC_DEPTH_DATA_SCALE_DOWN_MODE_OFFSET) /* rectify, 2 byte per pixel but using 1 byte only */
- **#define APC_DEPTH_DATA_SCALE_DOWN_11_BITS** (APC_DEPTH_DATA_11_BITS + APC_DEPTH_DATA_SCALE_DOWN_MODE_OFFSET) /* rectify, 2 byte per pixel but using 11 bit only */
- **#define APC_DEPTH_DATA_SCALE_DOWN_OFF_RECTIFY** (APC_DEPTH_DATA_OFF_RECTIFY + APC_DEPTH_DATA_SCALE_DOWN_MODE_OFFSET) /* Rule 0.4b Reserved unused in any firmware */
- **#define APC_DEPTH_DATA_SCALE_DOWN_8_BITS_RAW** (APC_DEPTH_DATA_8_BITS_RAW + APC_DEPTH_DATA_SCALE_DOWN_MODE_OFFSET) /* raw */
- **#define APC_DEPTH_DATA_SCALE_DOWN_14_BITS_RAW** (APC_DEPTH_DATA_14_BITS_RAW + APC_DEPTH_DATA_SCALE_DOWN_MODE_OFFSET) /* raw */
- **#define APC_DEPTH_DATA_SCALE_DOWN_8_BITS_x80_RAW** (APC_DEPTH_DATA_8_BITS_x80_RAW + APC_DEPTH_DATA_SCALE_DOWN_MODE_OFFSET) /* raw */
- **#define APC_DEPTH_DATA_SCALE_DOWN_11_BITS_RAW** (APC_DEPTH_DATA_11_BITS_RAW + APC_DEPTH_DATA_SCALE_DOWN_MODE_OFFSET) /* raw */
- **#define APC_DEPTH_DATA_SCALE_DOWN_14_BITS_COMBINED_RECTIFY** (APC_DEPTH_DATA_14_BITS_COMBINED_RECTIFY + APC_DEPTH_DATA_SCALE_DOWN_MODE_OFFSET) /* Rule 0.4b Reserved unused in any firmware */
- **#define APC_DEPTH_DATA_SCALE_DOWN_11_BITS_COMBINED_RECTIFY** (APC_DEPTH_DATA_11_BITS_COMBINED_RECTIFY + APC_DEPTH_DATA_SCALE_DOWN_MODE_OFFSET) /* Rule 0.4b Reserved unused in any firmware */
- **#define APC_DEPTH_DATA_SCALE_DOWN_ILM_OFF_RAW** (APC_DEPTH_DATA_SCALE_DOWN_OFF_RAW + APC_DEPTH_DATA_INTERLEAVE_MODE_OFFSET) /* raw (depth off, only raw color) */
- **#define APC_DEPTH_DATA_SCALE_DOWN_ILM_DEFAULT** (APC_DEPTH_DATA_SCALE_DOWN_DEFAULT + APC_DEPTH_DATA_INTERLEAVE_MODE_OFFSET) /* raw (depth off, only raw color) */
- **#define APC_DEPTH_DATA_SCALE_DOWN_ILM_8_BITS** (APC_DEPTH_DATA_SCALE_DOWN_8_BITS + APC_DEPTH_DATA_INTERLEAVE_MODE_OFFSET) /* rectify, 1 byte per pixel */

- `#define APC_DEPTH_DATA_SCALE_DOWN_ILM_14_BITS` (APC_DEPTH_DATA_SCALE_DOWN_14←
_BITS + APC_DEPTH_DATA_INTERLEAVE_MODE_OFFSET) /* rectify, 2 byte per pixel */
- `#define APC_DEPTH_DATA_SCALE_DOWN_ILM_8_BITS_x80` (APC_DEPTH_DATA_SCALE_DOWN_←
_8_BITS_x80 + APC_DEPTH_DATA_INTERLEAVE_MODE_OFFSET) /* rectify, 2 byte per pixel but using 1
byte only */
- `#define APC_DEPTH_DATA_SCALE_DOWN_ILM_11_BITS` (APC_DEPTH_DATA_SCALE_DOWN_11←
_BITS + APC_DEPTH_DATA_INTERLEAVE_MODE_OFFSET) /* rectify, 2 byte per pixel but using 11 bit
only */
- `#define APC_DEPTH_DATA_SCALE_DOWN_ILM_OFF_RECTIFY` (APC_DEPTH_DATA_SCALE_DO←
WN_OFF_RECTIFY + APC_DEPTH_DATA_INTERLEAVE_MODE_OFFSET) /* rectify (depth off, only
rectify color) */
- `#define APC_DEPTH_DATA_SCALE_DOWN_ILM_8_BITS_RAW` (APC_DEPTH_DATA_SCALE_DOW←
N_8_BITS_RAW + APC_DEPTH_DATA_INTERLEAVE_MODE_OFFSET) /* raw */
- `#define APC_DEPTH_DATA_SCALE_DOWN_ILM_14_BITS_RAW` (APC_DEPTH_DATA_SCALE_DO←
WN_14_BITS_RAW + APC_DEPTH_DATA_INTERLEAVE_MODE_OFFSET) /* raw */
- `#define APC_DEPTH_DATA_SCALE_DOWN_ILM_8_BITS_x80_RAW` (APC_DEPTH_DATA_SCALE_D←
OWN_8_BITS_x80_RAW + APC_DEPTH_DATA_INTERLEAVE_MODE_OFFSET) /* raw */
- `#define APC_DEPTH_DATA_SCALE_DOWN_ILM_11_BITS_RAW` (APC_DEPTH_DATA_SCALE_DO←
WN_11_BITS_RAW + APC_DEPTH_DATA_INTERLEAVE_MODE_OFFSET) /* raw */
- `#define APC_DEPTH_DATA_SCALE_DOWN_ILM_14_BITS_COMBINED_RECTIFY` (APC_DEPTH_DA←
TA_SCALE_DOWN_14_BITS_COMBINED_RECTIFY + APC_DEPTH_DATA_INTERLEAVE_MODE_OF←
FSET)
- `#define APC_DEPTH_DATA_SCALE_DOWN_ILM_11_BITS_COMBINED_RECTIFY` (APC_DEPTH_DA←
TA_SCALE_DOWN_11_BITS_COMBINED_RECTIFY + APC_DEPTH_DATA_INTERLEAVE_MODE_OF←
FSET)
- `#define APC_READ_FLASH_TOTAL_SIZE` 128
- `#define APC_READ_FLASH_FW_PLUGIN_SIZE` 104
- `#define APC_WRITE_FLASH_TOTAL_SIZE` 128
- `#define APC_Y_OFFSET_FILE_ID_0` 30
- `#define APC_Y_OFFSET_FILE_SIZE` 256
- `#define APC_RECTIFY_FILE_ID_0` 40
- `#define APC_RECTIFY_FILE_SIZE` 1024
- `#define APC_ZD_TABLE_FILE_ID_0` 50
- `#define APC_ZD_TABLE_FILE_SIZE_8_BITS` 512
- `#define APC_ZD_TABLE_FILE_SIZE_11_BITS` 4096
- `#define APC_CALIB_LOG_FILE_ID_0` 240
- `#define APC_CALIB_LOG_FILE_SIZE` 4096
- `#define APC_USER_DATA_FILE_ID_0` 200
- `#define APC_USER_DATA_FILE_SIZE_0` 1024
- `#define APC_USER_DATA_FILE_SIZE_1` 4096
- `#define APC_BACKUP_USER_DATA_FILE_ID` 201
- `#define APC_BACKUP_USER_DATA_SIZE` 1024
- `#define APC_PID_8029` 0x0568
- `#define APC_PID_8030` APC_PID_8029
- `#define APC_PID_8039` APC_PID_8029
- `#define APC_PID_8031` 0x0117
- `#define APC_PID_8032` 0x0118
- `#define APC_PID_8036` 0x0120
- `#define APC_PID_8037` 0x0121
- `#define APC_PID_8038` 0x0124
- `#define APC_PID_8038_M0` APC_PID_8038
- `#define APC_PID_8038_M1` 0x0147
- `#define APC_PID_8040W` 0x0130
- `#define APC_PID_8040S` 0x0131
- `#define APC_PID_8040S_K` 0x0149

- #define **APC_PID_8041** 0x0126
- #define **APC_PID_8042** 0x0127
- #define **APC_PID_8043** 0x0128
- #define **APC_PID_8044** 0x0129
- #define **APC_PID_8045K** 0x0134
- #define **APC_PID_8046K** 0x0135
- #define **APC_PID_8051** 0x0136
- #define **APC_PID_8052** 0x0137
- #define **APC_PID_8053** 0x0138
- #define **APC_PID_8054** 0x0139
- #define **APC_PID_8054_K** 0x0143
- #define **APC_PID_8059** 0x0146
- #define **APC_PID_8060** 0x0152
- #define **APC_PID_8060_K** 0x0150
- #define **APC_PID_8060_T** 0x0151
- #define **APC_PID_AMBER** 0x0112
- #define **APC_PID_SALLY** 0x0158
- #define **APC_PID_HYPATIA** 0x0160
- #define **APC_PID_HYPATIA2** 0x0173
- #define **APC_PID_HYPATIA4** 0x0204
- #define **APC_PID_8062** 0x0162
- #define **APC_PID_8063** 0x0164
- #define **APC_PID_8063_K** 0x0165
- #define **APC_PID_8072** 0x0180
- #define **APC_PID_8076** 0x0181
- #define **APC_PID_80362** APC_PID_8076
- #define **APC_PID_8077** 0x0182
- #define **APC_PID_8081** 0x0183
- #define **APC_PID_IRIS** 0x0184
- #define **APC_PID_IVY** 0x0177
- #define **APC_PID_IVY2** 0x0191
- #define **APC_PID_IVY3** 0x0192
- #define **APC_PID_IVY2_S** 0x0195
- #define **APC_PID_IVY4** 0x0198
- #define **APC_PID_80363C** 0x0202
- #define **APC_PID_80363IR** 0x0211
- #define **APC_PID_GRAPE** 0x0202
- #define **APC_PID_GRAP** 0x0179
- #define **APC_PID_GRAP_K** 0x0000
- #define **APC_PID_GRAP_SLAVE** 0x0279
- #define **APC_PID_GRAP_SLAVE_K** 0x0283
- #define **APC_PID_BOOTLOADER** 0x0668
- #define **APC_PID_GRAP_THERMAL** 0xf9f9
- #define **APC_PID_GRAP_THERMAL2** 0xf8f8
- #define **APC_PID_MIPI_8036** (APC_PID_8036 | 0xf000)
- #define **APC_PID_NORA** 0x0168
- #define **APC_PID_HELEN** 0x0171
- #define **APC_PID_SANDRA** 0x0167
- #define **APC_VID_GRAP_THERMAL** 0x04b4
- #define **APC_VID_2170** 0x0110
- #define **APC_VID_EEVER** 0x1e4e
- #define **APC_VID_EYS3D** 0x3438
- #define **CT_PROPERTY_ID** 1
- #define **PU_PROPERTY_ID** 3
- #define **CT_PROPERTY_ID_AUTO_EXPOSURE_MODE_CTRL** 0

- #define CT_PROPERTY_ID_AUTO_EXPOSURE_PRIORITY_CTRL 1
- #define CT_PROPERTY_ID_EXPOSURE_TIME_ABSOLUTE_CTRL 2
- #define CT_PROPERTY_ID_EXPOSURE_TIME_RELATIVE_CTRL 3
- #define CT_PROPERTY_ID_FOCUS_ABSOLUTE_CTRL 4
- #define CT_PROPERTY_ID_FOCUS_RELATIVE_CTRL 5
- #define CT_PROPERTY_ID_FOCUS_AUTO_CTRL 6
- #define CT_PROPERTY_ID_IRIS_ABSOLUTE_CTRL 7
- #define CT_PROPERTY_ID_IRIS_RELATIVE_CTRL 8
- #define CT_PROPERTY_ID_ZOOM_ABSOLUTE_CTRL 9
- #define CT_PROPERTY_ID_ZOOM_RELATIVE_CTRL 10
- #define CT_PROPERTY_ID_PAN_ABSOLUTE_CTRL 11
- #define CT_PROPERTY_ID_PAN_RELATIVE_CTRL 12
- #define CT_PROPERTY_ID_TILT_ABSOLUTE_CTRL 13
- #define CT_PROPERTY_ID_TILT_RELATIVE_CTRL 14
- #define CT_PROPERTY_ID_PRIVACY_CTRL 15
- #define PU_PROPERTY_ID_BACKLIGHT_COMPENSATION_CTRL 0
- #define PU_PROPERTY_ID_BRIGHTNESS_CTRL 1
- #define PU_PROPERTY_ID_CONTRAST_CTRL 2
- #define PU_PROPERTY_ID_GAIN_CTRL 3
- #define PU_PROPERTY_ID_POWER_LINE_FREQUENCY_CTRL 4
- #define PU_PROPERTY_ID_HUE_CTRL 5
- #define PU_PROPERTY_ID_HUE_AUTO_CTRL 6
- #define PU_PROPERTY_ID_SATURATION_CTRL 7
- #define PU_PROPERTY_ID_SHARPNESS_CTRL 8
- #define PU_PROPERTY_ID_GAMMA_CTRL 9
- #define PU_PROPERTY_ID_WHITE_BALANCE_CTRL 10
- #define PU_PROPERTY_ID_WHITE_BALANCE_AUTO_CTRL 11
- #define AE_MOD_MANUAL_MODE 0x01
- #define AE_MOD_AUTO_MODE 0x02
- #define AE_MOD_SHUTTER_PRIORITY_MODE 0x04
- #define AE_MOD_APERTURE_PRIORITY_MODE 0x03
- #define PU_PROPERTY_ID_AWB_DISABLE 0
- #define PU_PROPERTY_ID_AWB_ENABLE 1
- #define FW_FID_GROUP_OFFSET 5
- #define CT_PROPERTY_ID_EXPOSURE 4
- #define POSTPAR_HR_MODE 5
- #define POSTPAR_HR_CURVE_0 6
- #define POSTPAR_HR_CURVE_1 7
- #define POSTPAR_HR_CURVE_2 8
- #define POSTPAR_HR_CURVE_3 9
- #define POSTPAR_HR_CURVE_4 10
- #define POSTPAR_HR_CURVE_5 11
- #define POSTPAR_HR_CURVE_6 12
- #define POSTPAR_HR_CURVE_7 13
- #define POSTPAR_HR_CURVE_8 14
- #define POSTPAR_HF_MODE 17
- #define POSTPAR_DC_MODE 20
- #define POSTPAR_DC_CNT_THD 21
- #define POSTPAR_DC_GRAD_THD 22
- #define POSTPAR_SEG_MODE 23
- #define POSTPAR_SEG_THD_SUB 24
- #define POSTPAR_SEG_THD_SLP 25
- #define POSTPAR_SEG_THD_MAX 26
- #define POSTPAR_SEG_THD_MIN 27
- #define POSTPAR_SEG_FILL_MODE 28

- `#define POSTPAR_HF2_MODE 31`
- `#define POSTPAR_GRAD_MODE 34`
- `#define POSTPAR_TEMP0_MODE 37`
- `#define POSTPAR_TEMP0_THD 38`
- `#define POSTPAR_TEMP1_MODE 41`
- `#define POSTPAR_TEMP1_LEVEL 42`
- `#define POSTPAR_TEMP1_THD 43`
- `#define POSTPAR_FC_MODE 46`
- `#define POSTPAR_FC_EDGE_THD 47`
- `#define POSTPAR_FC_AREA_THD 48`
- `#define POSTPAR_MF_MODE 51`
- `#define POSTPAR_ZM_MODE 52`
- `#define POSTPAR_RF_MODE 53`
- `#define POSTPAR_RF_LEVEL 54`

Typedefs

- `typedef unsigned char BYTE`
- `typedef signed int BOOL`
- `typedef unsigned short WORD`
- `typedef struct packet\_s srb_packet_s`
- `typedef struct tagDEVINFORMATION DEVINFORMATION`
- `typedef struct tagDEVINFORMATION * PDEVINFORMATION`
- `typedef struct tagDEVSEL DEVSELINFO`
- `typedef struct tagDEVSEL * PDEVSELINFO`
- `typedef struct tagAPC\_STREAM\_INFO APC_STREAM_INFO`
- `typedef struct tagAPC\_STREAM\_INFO * PAPC_STREAM_INFO`
- `typedef struct tagZDTableInfo ZDTABLEINFO`
- `typedef struct tagZDTableInfo * PZDTABLEINFO`
- `typedef struct tagKEEP\_DATA\_CTRL KEEP_DATA_CTRL`
- `typedef enum AE_STATUS * PAE_STATUS`
- `typedef enum AWB_STATUS * PAWB_STATUS`
- `typedef struct eSPCtrl\_RectLogData eSPCtrl_RectLogData`
- `typedef struct GyroTag GYRO_ANGULAR_RATE_DATA`
- `typedef struct AccelerationTag ACCELERATION_DATA`
- `typedef struct CompassTag COMPASS_DATA`
- `typedef void(* APC_ImgCallbackFn) (APCImageType::Value imgType, int imgId, unsigned char *imgBuf, int imgSizeByte, int width, int height, int serialNumber, long long timestamp, void *pParameter)`

Enumerations

- `enum SENSORMODE_INFO {
 SENSOR_A = 0, SENSOR_B, SENSOR_BOTH, SENSOR_C,
 SENSOR_D}`
- `enum PIXEL_FMT {
 YUV22_YUYV_PIXEL_FMT = 0, YUV22_UYVY_PIXEL_FMT, RAW10_GBRG_PIXEL_FMT, RAW10_BGRG_PIXEL_FMT,
 RAW10_RGBG_PIXEL_FMT, RAW10_GRBG_PIXEL_FMT, MJPEG_PIXEL_FMT, UNKOWN_PIXEL_FMT = 0xffff }`
- `enum DEVICE_TYPE {
 OTHERS = 0, AXES1, PUMA, KIWI,
 PLUM, GRAPE, UNKNOWN_DEVICE_TYPE = 0xffff }`

- enum **FLASH_DATA_TYPE** {
Total = 0, **FW_PLUGIN**, **BOOTLOADER_ONLY**, **FW_ONLY**,
PLUGIN_ONLY, **UNP** }
- enum **USERDATA_SECTION_INDEX** {
USERDATA_SECTION_0 = 0, **USERDATA_SECTION_1**, **USERDATA_SECTION_2**, **USERDATA_SECTION_3**,
USERDATA_SECTION_4, **USERDATA_SECTION_5**, **USERDATA_SECTION_6**, **USERDATA_SECTION_7**,
USERDATA_SECTION_8, **USERDATA_SECTION_9** }
- enum **CALIBRATION_LOG_TYPE** {
ALL_LOG = 0, **SERIAL_NUMBER**, **PRJFILE_LOG**, **STAGE_TIME_RESULT_LOG**,
SENSOR_OFFSET, **AUTO_ADJUST_LOG**, **RECTIFY_LOG**, **ZD_LOG**,
DEPTHMAP_KOG }
- enum **CONTROL_MODE** {
IMAGE_SN_NONSYNC = 0, **IMAGE_SN_SYNC**, **IMAGE_NORECTIFY_DATA** = 100, **IMAGE_RECTIFY_DATA**,
IMAGE_USERPTR_MODE = 200 }
- enum **DEPTH_TRANSFER_CTRL** { **DEPTH_IMG_NON_TRANSFER**, **DEPTH_IMG_GRAY_TRANSFER**,
DEPTH_IMG_COLORFUL_TRANSFER }
- enum **SENSOR_TYPE_NAME** {
APC_SENSOR_TYPE_H22 = 0, **APC_SENSOR_TYPE_H65** = 1, **APC_SENSOR_TYPE_OV7740** = 2, **APC_SENSOR_TYPE_AR0134** = 3,
APC_SENSOR_TYPE_AR0135 = 4, **APC_SENSOR_TYPE_AR0144** = 5, **APC_SENSOR_TYPE_AR0330** = 6, **APC_SENSOR_TYPE_AR0522** = 7,
APC_SENSOR_TYPE_AR1335 = 8, **APC_SENSOR_TYPE_OV9714** = 9, **APC_SENSOR_TYPE_OV9282** = 10, **APC_SENSOR_TYPE_H68** = 11,
APC_SENSOR_TYPE_OV2740 = 12, **APC_SENSOR_TYPE_OC0SA10** = 13, **APC_SENSOR_TYPE_VD56G3** = 14, **APC_SENSOR_TYPE_VD66GY** = 15,
APC_SENSOR_TYPE_SC2356 = 16, **APC_SENSOR_TYPE_OG02B10** = 17, **APC_SENSOR_TYPE_OG02B1B** = 18, **APC_SENSOR_TYPE_UNKOWN** = 0xffff }
- enum **AE_STATUS** { **AE_ENABLE** = 0, **AE_DISABLE** }
- enum **AWB_STATUS** { **AWB_ENABLE** = 0, **AWB_DISABLE** }
- enum **USB_PORT_TYPE** { **USB_PORT_TYPE_2_0** = 2, **USB_PORT_TYPE_3_0**, **MIPI_PORT_TYPE**, **USB_PORT_TYPE_UNKNOW** }
- enum **SENSITIVITY_LEVEL_L3G** { **DPS_245** = 0, **DPS_500**, **DPS_2000** }
- enum **SENSITIVITY_LEVEL_LSM** {
_2G = 0, **_4G**, **_6G**, **_8G**,
_16G }
- enum **OUTPUT_DATA_RATE** {
One_Shot = 0, **_1_HZ_1_HZ**, **_7_HZ_1_HZ**, **_12_5_HZ_1_HZ**,
_25_HZ_1_HZ, **_7_HZ_7_HZ**, **_12_5_HZ_12_5_HZ**, **_25_HZ_25_HZ** }
- enum **POWER_STATE** { **POWER_ON** = 0, **POWER_OFF** }
- enum **BRIGHTNESS_LEVEL** {
LEVEL_0 = 0, **LEVEL_1**, **LEVEL_2**, **LEVEL_3**,
LEVEL_4, **LEVEL_5**, **LEVEL_6**, **LEVEL_7**,
LEVEL_8, **LEVEL_9**, **LEVEL_10**, **LEVEL_11**,
LEVEL_12, **LEVEL_13**, **LEVEL_14**, **LEVEL_15** }

5.2.1 Detailed Description

error/data type definitions

Copyright:

This file copyright (C) 2021 by eYs3D Microelectronics, Co.

An unpublished work. All rights reserved.

This file is proprietary information, and may not be disclosed or copied without the prior permission of eYs3D Microelectronics, Co.

Index

APC_META_DATA, [7](#)

APCImageType, [7](#)

AccelerationTag, [7](#)

CamDist1

 eSPCtrl_RectLogData, [11](#)

CamDist2

 eSPCtrl_RectLogData, [11](#)

CamMat1

 eSPCtrl_RectLogData, [11](#)

CamMat2

 eSPCtrl_RectLogData, [11](#)

CompassTag, [8](#)

DECIMATION_PARAMS, [8](#)

DEVINFORMATIONEX, [8](#)

 nChipID, [9](#)

 nDevType, [9](#)

 strDevName, [9](#)

 strDevPath, [9](#)

 wPID, [9](#)

 wUsbNode, [9](#)

 wVID, [10](#)

Date

 eSPCtrl_RectLogData, [11](#)

eSPCtrl_RectLogData, [10](#)

 CamDist1, [11](#)

 CamDist2, [11](#)

 CamMat1, [11](#)

 CamMat2, [11](#)

 Date, [11](#)

 InImgHeight, [11](#)

 InImgWidth, [11](#)

 LRotaMat, [11](#)

 nLineBuffers, [12](#)

 NewCamMat1, [11](#)

 NewCamMat2, [12](#)

 OutImgHeight, [12](#)

 OutImgWidth, [12](#)

 RECT_AvgErr, [12](#)

 RECT_Crop_Col_BG_L, [12](#)

 RECT_Crop_Col_ED_L, [12](#)

 RECT_Crop_Row_BG, [12](#)

 RECT_Crop_Row_ED, [12](#)

 RECT_CropEnable, [12](#)

 RECT_Scale_Col_M, [13](#)

 RECT_Scale_Col_N, [13](#)

 RECT_Scale_Row_M, [13](#)

 RECT_Scale_Row_N, [13](#)

 RECT_ScaleEnable, [13](#)

 RECT_ScaleHeight, [13](#)

 RECT_ScaleWidth, [13](#)

 RRotaMat, [13](#)

 RotaMat, [13](#)

 TranMat, [13](#)

 uByteArray, [14](#)

eSPDI/eSPDI.h, [19](#)

eSPDI/eSPDI_def.h, [19](#)

GyroTag, [14](#)

InImgHeight

 eSPCtrl_RectLogData, [11](#)

InImgWidth

 eSPCtrl_RectLogData, [11](#)

LRotaMat

 eSPCtrl_RectLogData, [11](#)

nChipID

 DEVINFORMATIONEX, [9](#)

nDevType

 DEVINFORMATIONEX, [9](#)

nLineBuffers

 eSPCtrl_RectLogData, [12](#)

NewCamMat1

 eSPCtrl_RectLogData, [11](#)

NewCamMat2

 eSPCtrl_RectLogData, [12](#)

OutImgHeight

 eSPCtrl_RectLogData, [12](#)

OutImgWidth

 eSPCtrl_RectLogData, [12](#)

POST_PROCESS_PARAMS, [16](#)

packet_s, [14](#)

PointCloudInfo, [15](#)

RECT_AvgErr

 eSPCtrl_RectLogData, [12](#)

RECT_Crop_Col_BG_L

 eSPCtrl_RectLogData, [12](#)

RECT_Crop_Col_ED_L

 eSPCtrl_RectLogData, [12](#)

RECT_Crop_Row_BG

 eSPCtrl_RectLogData, [12](#)

RECT_Crop_Row_ED

 eSPCtrl_RectLogData, [12](#)

RECT_CropEnable

- eSPCtrl_RectLogData, [12](#)
- RECT_Scale_Col_M
 - eSPCtrl_RectLogData, [13](#)
- RECT_Scale_Col_N
 - eSPCtrl_RectLogData, [13](#)
- RECT_Scale_Row_M
 - eSPCtrl_RectLogData, [13](#)
- RECT_Scale_Row_N
 - eSPCtrl_RectLogData, [13](#)
- RECT_ScaleEnable
 - eSPCtrl_RectLogData, [13](#)
- RECT_ScaleHeight
 - eSPCtrl_RectLogData, [13](#)
- RECT_ScaleWidth
 - eSPCtrl_RectLogData, [13](#)
- RRotaMat
 - eSPCtrl_RectLogData, [13](#)
- RotaMat
 - eSPCtrl_RectLogData, [13](#)
- strDevName
 - DEVINFORMATIONEX, [9](#)
- strDevPath
 - DEVINFORMATIONEX, [9](#)
- tagAPC_STREAM_INFO, [16](#)
- tagDEVINFORMATION, [16](#)
- tagDEVSEL, [16](#)
- tagKEEP_DATA_CTRL, [17](#)
- tagZDTableInfo, [17](#)
- TranMat
 - eSPCtrl_RectLogData, [13](#)
- uByteArray
 - eSPCtrl_RectLogData, [14](#)
- wPID
 - DEVINFORMATIONEX, [9](#)
- wUsbNode
 - DEVINFORMATIONEX, [9](#)
- wVID
 - DEVINFORMATIONEX, [10](#)